

Upgrade Method by USB flash drive

[How to prepare Software Update file via USB flash drive]

1. Download the newest software file onto your computer from www.samsung.com.
2. If the software file is compressed (*.zip), the file should be uncompressed.
(*ROM file is Backend upgrade file and *.ssp file is Frontend upgrade file)
3. Connect a USB flash drive to your computer.
4. If there are previous versions of software on USB flash drive, please delete them.
5. Copy the software file to USB flash drive. (Copy the file in USB root directory as below)




- ※ *.ROM file and *.ssp file must be copied to a different USB flash drive.
Please do not save them to the same USB flash drive.
- ※ Do not update all file at once, you can only do one at a time.

[Warning]

1. The following events may interrupt the upgrade process and
MAY RESULT IN PERMANENT DAMAGE TO THE UNIT.
 - 1) Unplugging the power cord while upgrades are being applied.
 - 2) Power Outage while upgrades are being applied.
 - 3) Remove the USB drive while upgrades are being applied.
2. Please do not save *.ROM file and *.ssp file to the same USB flash drive.
3. Please do not re-name software file.
We do not guarantee any defects caused by re-naming software file.

[How to upgrade Software]

1. Power on the device. Connect the USB device containing the newest software file to the USB port on the back of the product.
2. Press the (**F.**) button on the main unit's top panel or the  (SOURCE) button on the remote control to select the USB mode

3. Software will be upgraded automatically and then the main unit will turn off automatically after completing the software upgrade.
4. Once upgrading the product software is completed, the initializing is needed.
Turn off the product(standby mode) and then press PLAY/PAUSE(▶||) button for a while (about 5 seconds) to initialize the product.
After that, you can see the "INIT" message on the display.

※ After reset, all settings are reset to their factory default settings. We recommend you write down your settings so that you can easily reset them after the update.